



XYZ (ASCII Point File)

- ▶ Importing an XYZ Tab Delimited Point File
- ▶ Exporting to an XYZ Tab Delimited Row/Column Point File
- ▶ Exporting to an XYZ Tab Delimited UTM Point File
- ▶ Exporting to an XYZ Tab Delimited X/Y Point File

File Type: TEXT (XYZ Point File)

Directions: XYZ<->MF

Details: This translator will import and export text files composed of a list of points. Each point is expected to have an X and Y coordinate, a Z value separated by tab characters, and be terminated with a carriage return (*i.e.*, X<tab>Y<tab>Z<return>). The X and Y coordinates may be row/column, latitude/longitude, UTM, or a user defined X/Y system. The Z value may be either fixed point/integer or floating point/real. To be recognized by the translator, XYZ files must have the “.xyz” extension.

XYZ files are produced commonly by GPS (Global Positioning System) units and other field data collection methods. The data are typically sparse points referenced to a real-world coordinate system like Latitude/Longitude or UTM. A user defined grid can also be used to reference data points within a mapped area. This is particularly useful when surveying points across UTM boundaries.

GPS units gather X/Y positional coordinates for points and any number of attributes attached to those points. One XYZ file should be generated for each attribute that you want to map. Descriptive text can be appended to your imported XYZ data by using the **Tab Delimited Text** translator to import legend text.

When you are exporting to an XYZ file you can retain the legend text by using the **Tab Delimited Text** translator to **export legend text**.



MFworks Translators

Importing an XYZ Tab Delimited Point File

- Import Dialog**
- ▶ Using the translator dialog box interface
 - ▶ Using the dialog box interface to create or edit scripts

XYZ Point file Import

Coordinate Range:

North: West:

South: East:

Grid size:

Collision: Replace Add Origin: BY LR

The XYZ Point translator takes a tab delimited file that contains point data organized in three columns. The first two columns are a row, X, or longitude coordinate and a column, Y, or latitude coordinate. The last column is a data value for the point.

Coordinate Range/Scan For Range

Use the **North**, **South**, **East**, and **West** fields to specify the extents of the map data. These values must reflect the coordinate system of the input file. To have these fields populated automatically, click on the **Scan For Range** button. This will determine the outermost extents of the input file and place the values in the appropriate fields.

These values can be modified to extract only a portion of the file or to specify a map layer that exceeds the extents of the input data. To do so, click in the appropriate field and enter the new value. These values may be true X-Y coordinates, UTM coordinates, or latitude/ longitude coordinates depending on the referencing system in the coverage file.

Grid Size

The **Grid size** field is used to specify the grid interval of the resulting map layer. This value will become the cell resolution of the new map layer. **The value for this option must be expressed in the coordinate system of the input file.**

If the coordinate system of the input map layer is **latitude and longitude**, then the value specified for the **Grid size** option should be the number of **degrees** per cell side (specify **None** for units). Future releases of this translator will allow you to specify a cell resolution in metres. For users with



MFworks Translators

a background in programming, ThinkSpace Inc. has a C routine available to convert latitude and longitude grid sizes to metres; after you have imported a map layer with a latitude and longitude coordinate system, you can convert your degrees per cell side cell resolution to metres per cell side.

If the coordinate system of the input map layer is **UTM** (Universal Transverse Mercator), then the value specified for the **Grid size** option should be the number of **UTM metres** per cell side.

The smaller (*i.e.*, finer) the grid size, the higher the cell resolution (*i.e.*, the greater the number of cells).

Collision

If a coordinate point occurs more than once in the input file, a conflict results. Click on the **Replace** radio button to have the last occurrence of the point in the file replace any previous occurrences. Click on the **Add** radio button to have the Z value of coincidental points added together in the output map layer.

Origin

Use this option to identify the location of the origin of the input file coordinate system. X/Y and longitude/latitude have an origin in the lower left hand corner of the map. MFworks uses a row/column coordinate system with the origin in the upper left hand corner of the map layer.

Import Syntax

- ▶ [Syntax and type conventions](#)
- ▶ [Using the Script window interface](#)
- ▶ [Using the dialog box interface to create or edit scripts](#)

```
Import input file Using "Text (Point File)"
    North value South value West value East value
    GridSize value
    [ReplacePoints | AddPoints]
    [LowerLeftOrigin | UpperLeftOrigin];
```

```
North value
South value
West value
East value
```

These options specify the extent of the area in the point file to be rasterized. These values must reflect the coordinate system of the input file. The values may be modified to extract only a portion of the file or to specify a map layer that exceeds the extents of the input data. Enter appropriate values following each modifier. These values may be true X-Y coordinates, UTM



MFworks Translators

coordinates, or latitude/longitude coordinates depending on the referencing system in the coverage file.

GridSize *value*

The GridSize modifier is used to specify the grid interval of the resulting map layer. This value will become the cell resolution of the new map layer. **The value for this option must be expressed in the coordinate system of the input file.**

If the coordinate system of the input map layer is **latitude and longitude**, then the value specified for the GridSize option should be the number of **degrees** per cell side (do not specify units). Future releases of this translator will allow you to specify a cell resolution in metres. For users with a background in programming, ThinkSpace Inc. has a C routine available to convert latitude and longitude grid sizes to metres; after you have imported a map layer with a latitude and longitude coordinate system, you can convert your degrees per cell side cell resolution to metres per cell side.

If the coordinate system of the input map layer is **UTM** (Universal Transverse Mercator), then the value specified for the **Grid size** option should be the number of **UTM metres** per cell side.

The smaller (*i.e.*, finer) the grid size, the higher the cell resolution (*i.e.*, the greater the number of cells).

ReplacePoints

AddPoints

If a coordinate point occurs more than once in the input file, a conflict results. Choose **ReplacePoints** to have the last occurrence of the point in the file replace any previous occurrences. Specify **AddPoints** to have the Z value of coincidental points added to any previous occurrences point in the output map layer.

LowerLeftOrigin

UpperLeftOrigin

Use these modifiers to identify the origin of the input file coordinate system. X/Y and longitude/latitude have an origin in the lower left hand corner of the map. MFworks uses a row/column coordinate system with the origin being in the upper left hand corner of the map layer. In a **script statement**, if this modifier is not specified for the input file, the origin is assumed to be the upper left hand corner, by default.



MFworks Translators

Import Example Importing an XYZ Tab Delimited Point File

A set of coordinate points and attribute values were collected using a GPS (Global Positioning System) unit. The data are exported to a spreadsheet program where separate XYZ files are generated for each attribute:

	A	B	C
1	0	1	30
2	5	66	75
3	6	12	55
4	12	51	30
5	15	26	30
6	15	70	30
7	17	40	30
8	18	87	45
9	20	48	75
10	24	76	55
11	31	59	30
12	32	16	30
13	35	23	55
14	35	37	30
15	36	48	45
16	42	71	30
17	46	87	45
18	49	31	55
19	49	35	30
20	51	49	30
21	53	19	45
22	54	52	45
23	57	0	30
24	58	63	45
25	64	71	55
26	65	27	55
27	69	0	75
28	69	40	45
29	70	63	45
30	71	23	45
31	78	61	30
32	82	18	30
33	88	99	30
34	90	43	45
35	98	7	75
36	98	24	75
37	99	54	30



MFworks Translators

The spreadsheet files are then exported as tab delimited ASCII text files. Each line represents a point in space and an associated value:

```

0 -> 1 -> 309
5 -> 66 -> 759
6 -> 12 -> 559
12 -> 51 -> 309
15 -> 26 -> 309
15 -> 70 -> 309
17 -> 40 -> 309
18 -> 87 -> 459
20 -> 48 -> 759
24 -> 76 -> 559
31 -> 59 -> 309
32 -> 16 -> 309
35 -> 23 -> 559
35 -> 37 -> 309
36 -> 48 -> 459
42 -> 71 -> 309
46 -> 87 -> 459
49 -> 31 -> 559
49 -> 35 -> 309
51 -> 49 -> 309
53 -> 19 -> 459
54 -> 52 -> 459
57 -> 0 -> 309
58 -> 63 -> 459
64 -> 71 -> 559
65 -> 27 -> 559
69 -> 0 -> 759
69 -> 40 -> 459
70 -> 63 -> 459
71 -> 23 -> 459
78 -> 61 -> 309
82 -> 18 -> 309
88 -> 99 -> 309
90 -> 43 -> 459
98 -> 7 -> 759
98 -> 24 -> 759
99 -> 54 -> 309


```

To convert this point data to an MFworks **map layer** select **Import Map** from the **File** menu. Select the file and choose **XYZ Point File (Text)** from the **Show Type** drop-down list. When the **Import XYZ Point File (Text)** dialog box appears the **Row/Column** origin radio button is clicked, then the



MFworks Translators


Scan For Range button is clicked. This causes the **Coordinate Range** fields to be populated automatically. The default **Replace** option is used:



If you were to execute this operation from the **Script window** the statement would be:

```
GPSPoints = Import "GPSPoints.txt"
    Using "Text (Point File)"
    North 0 South 99 West 0 East 99
    GridSize .2475 ReplacePoints
    UpperLeftOrigin;
```

When the map is displayed on screen, the default colour sequence will be applied to the map zones. Z values from the input file will be assigned as zone values:






MFworks Translators

When an XYZ Point file is imported, the **geometry** for the resulting map is generated automatically by the translator according to the coordinates of the original file.

Exporting to an XYZ Point File

- Export Dialog**
- ▶ Using the translator dialog box interface
 - ▶ Using the dialog box interface to create or edit scripts



The **Coordinate system** drop-down list options are based on existing geometries. Each built **geometry** will appear in this menu automatically. If no geometry exists for the map layer, then **Row/Column** with the origin in the top left hand corner appears by default.

- Export Syntax**
- ▶ Syntax and type conventions
 - ▶ Using the Script window interface
 - ▶ Using the dialog box interface to create or edit scripts

```
ExportMap map To output file
Using "Text (Point File)"
[Reference map [with geometry]];
```

Note: You must enclose the name of the referenced geometry with square brackets.



MFworks Translators


Reference with geometry

Use this modifier to specify the name of a **geometry** that has been built for the map layer to be exported. You can also specify a geometry from an alternate map layer. If no geometries have been built or this modifier has not been specified, then the Row/Column geometry with an origin in the top left hand corner of the map is assumed.

Export Example

Exporting to an XYZ Tab Delimited Row/Column Point File

A Geological Survey was conducted through this study area in the summer of 1998. Outcrops belonging to four formations were found in the area and a map layer was generated from GPS (Global Positioning System) readings. This mapped data is to be exported and used in a vector based Geological Modelling application:




The map data is to be exported in Row/Column format. **Export Map** is selected from the **File** menu. The name of the file and a file type of **XYZ** is specified in the **Save** file dialog box. When the **Export XYZ Point File**



MFworks Translators

(Text) dialog box is displayed **Row/Column** is selected from the **Coordinate system** drop-down list:



If you were to perform this command from the **Script window** the statement would be:

```
ExportMap "Summer 1998 Survey"  
  To "Summer 1998 Survey (RCZ)"  
  Using "Text (Point File)";
```

Before using the file in the Geological Modelling application the data are examined in a word processing application. XYZ files are tab delimited



MFworks Translators

ASCII text files that can be opened by most word processing and spreadsheet applications:

```

Summer 1998 Survey (RCZ).TXT
0 → 21 → 1009
2 → 110 → 1009
8 → 172 → 1009
22 → 75 → 1009
22 → 122 → 1009
25 → 128 → 1009
38 → 12 → 1009
43 → 34 → 1009
45 → 39 → 1009
55 → 116 → 1009
58 → 104 → 1009
73 → 145 → 2009
105 → 90 → 2009
119 → 92 → 2009
120 → 59 → 2009
157 → 34 → 2009
187 → 59 → 3009
190 → 21 → 2009
196 → 65 → 3009
234 → 189 → 4009
238 → 138 → 4009
243 → 38 → 3009
259 → 178 → 4009
261 → 12 → 3009
285 → 187 → 4009

```


Export Example Exporting to an XYZ Tab Delimited UTM Point File

A Geological Survey was conducted through this study area in the summer of 1998. Outcrops belonging to four formations were found in the area and a map layer was generated from GPS (Global Positioning System) readings.




MFworks Translators

This mapped data is to be exported and used in a vector based Geological Modelling application:



The map data is to be exported in UTM Northing/Easting format. **Export Map** is selected from the **File** menu. The name of the file and a file type of **XYZ** is specified in the **Save** file dialog box. When the **Export XYZ Point File (Text)** dialog box is displayed **UTM** is selected from the **Coordinate system** drop-down list:



If you were to perform this command from the **Script window** the statement would be:



MFworks Translators

```
ExportMap "Summer 1998 Survey"
  To "Summer 1998 Survey (UTM)"
  Using "Text (Point File)"
  Reference "Summer 1998 Survey" [UTM];
```

Before using the file in the Geological Modelling application the data are examined in a word processing application. XYZ files are tab delimited ASCII text files that can be opened by most word processing and spreadsheet applications:

```
49.889474 → 581.000000 → 100
227.421053 → 576.993103 → 100
351.094737 → 564.972414 → 100
157.605263 → 536.924138 → 100
251.357895 → 536.924138 → 100
263.326316 → 530.913793 → 100
31.936842 → 504.868966 → 100
75.821053 → 494.851724 → 100
85.794737 → 490.844828 → 100
239.389474 → 470.810345 → 100
215.452632 → 464.800000 → 100
297.236842 → 434.748276 → 200
187.526316 → 370.637931 → 200
191.515789 → 342.589655 → 200
125.689474 → 340.586207 → 200
75.821053 → 266.458621 → 200
125.689474 → 206.355172 → 300
49.889474 → 200.344828 → 200
137.657895 → 188.324138 → 300
385.005263 → 112.193103 → 400
283.273684 → 104.179310 → 400
83.800000 → 94.162069 → 300
363.063158 → 62.106897 → 400
31.936842 → 58.100000 → 300
381.015789 → 10.017241 → 400
```

Export Example Exporting to an XYZ Tab Delimited X/Y Point File



A Geological Survey was conducted through this study area in the summer of 1998. Outcrops belonging to four formations were found in the area and a map layer was generated from GPS (Global Positioning System) readings. This mapped data is to be exported and used in a vector based Geological Modelling application.

Before the file can be exported in an XYZ format, a new X/Y **geometry** must be built for the file to move the position of the origin from the top left hand corner to the bottom left hand corner. This simple process is outlined



MFworks Translators


in the figure below. First determine the Row/Column extents of the map layer, then mirror the positions vertically. Open the **Geometry Editor** dialog box by selecting **Edit Geometry** from the **Map** menu, and enter the Row/Column coordinates and their corresponding X/Y coordinates, specify a new name and click on the **Build** button. UTM Metres was selected from the **Format** drop-down list to give the correct numerical format to the output X/Y coordinates:






MFworks Translators

The new geometry can be checked by returning to the **Map window** and specifying the new geometry from the **Ruler Coordinates** sub menu of the **Map** menu:



Export Map is selected from the **File** menu. The name of the file and a file type of **XYZ** is specified in the **Save** file dialog box. When the **Export XYZ Point File (Text)** dialog box is displayed, the new geometry is selected from the **Coordinate system** drop-down list:



If you were to perform this command from the **Script window** the statement would be:



MFworks Translators

```
ExportMap "Summer 1998 Survey"
  To "Summer 1998 Survey (XYZ)"
  Using "Text (Point File)"
  Reference "Summer 1998 Survey" ["RC to XY"];
```

Before using the file in the Geological Modelling application the data are examined in a word processing application. XYZ files are tab delimited ASCII text files that can be opened by most word processing and spreadsheet applications:

